Nuance[®] Document Imaging

AutoStore

Version 7.0 SP3

Installation Guide



Contents

Installation of AutoStore 7.0	3
Prepare to install AutoStore	4 .4
Install AutoStore	7
Upgrade a previous installation of AutoStore	8 .8 .9
License AutoStore1	1
AutoStore tutorial1	7
Communication port reference23	3
Troubleshooting tips	1



Installation of AutoStore 7.0

This guide describes options and procedures to install or upgrade AutoStore server and how to license installed components.

The installation installs the AutoStore server and workflow components for capturing, processing, and routing of documents within an enterprise. Client applications included with the installation can be installed separately on the server on distributed to install on user workstations.

During installation of the server, you can accept the default settings or select to install individual components. After installation of the server, availability of installed components depends on licensing.

Section	Description
Prepare for Installation	 Describes how to prepare a computer for AutoStore: System requirements Download software Turn of Microsoft Windows Firewall
Install AutoStore	Steps through a new install of AutoStore 7.0.
Upgrade AutoStore	Describes steps to upgrade from a previous version of A utoStore.
License AutoStore	Describes how to license AutoStore server and its comp onents.
AutoStore tutorial	Describes how start the AutoStore Process Designer and build and run a simple workflow.
Communication port reference	Provides general information on ports and protocols for AutoStore components.
Troubleshooting tips	Provides tips to solve known issues.

In This Guide



Prepare to install AutoStore

Depending on your requirements, the AutoStore 7.0 setup application installs a new instance of AutoStore, upgrades an existing instance, or provides maintenance options. Topics in this section address important considerations for the computer where AutoStore will be installed. Before you install AutoStore review the information in this section.

System requirements

This topic describes system prerequisites before you run setup for AutoStore 7.0.

Category	Requirement
Processor	Small deployment recommendation:
	• Single dual core desktop CPU — 2 GHz or higher
	Medium deployment recommendation:
	• XEON or Opteron CPU — 2MB or more 2nd-level cache, 1 or 2 CPUs/cores
	Large deployment recommendation:
	• XEON or Opteron CPU — 2MB or more 2nd-level cache, multiple CPUs/cores
Memory	Small deployment recommendation:
	• 2 GB of RAM
	Medium deployment recommendation:
	• 2—4 GB of RAM
	Large deployment recommendation:
	• At least 4 GB of RAM
Hard disk space	Small deployment recommendation:
	• 10 GB
	Medium deployment recommendation:
	• 40 GB
	Large deployment recommendation:
	• 100 GB
Network card	NIC card
Operating system	Server:
	Windows Server 2012 R2 — Standard and Datacenter
	Windows Server 2012 — Standard and Datacenter



Category	Requirement
	 Windows Server 2008 R2 — Standard, Enterprise, and Datacenter Windows Server 2008 (32\64 bit) — Standard, Enterprise, and Datacenter Windows 10 (32\64 bit) — Pro and Enterprise Windows 8.0*/8.1 (32\64 bit) — Pro and Enterprise Windows 7 (32\64 bit) — Professional, Ultimate, and Enterprise
	Note: Small Business Server / domain controllers are not supported for installing AutoStore.
	Client:
	 Windows 7 (32\64 bit) — Professional, Ultimate, and Enterprise Windows 8.0*/8.1 (32\64 bit) — Pro and Enterprise Windows 10 (32\64 bit) — Pro and Enterprise
	For all platforms, Microsoft recommends that you upgrade to the latest Windows Service Pack and critical updates available from the <i>Windows Update website</i> to ensure the best compatibility and security. Installation of the latest Windows Service Pack may be required on some operating systems.
Software	Internet browser for viewing Notable Solutions web Help:
	• Internet Explorer 9.0 or greater
	Edge on Windows 10 Eigen 4.0 an another
	 Fifelox 4.0 or greater Google Chrome 10.0 or greater
	Database management: †
	• Microsoft SQL Server Express $(32 \text{ bit})^{\ddagger}$
	Microsoft SQL Server 2005 (32-bit)
	Microsoft SQL Server 2008 (32- and 64-bit)
Framework	The AutoStore installation prompts to install required versions of Microsoft .NET Framework if they are not already available on a host machine.
	Microsoft .NET Framework 3.5
	Microsoft .NET Framework 4.0 Microsoft .NET Framework 4.5
Virtualization platform	This release of AutoStore has been tested for migrating virtual machines between phys ical servers with VMware VMotion.

Remaining prerequisites are installed during the installation process.

[‡] SQL Server Express is included with the AutoStore distributable as the default database server for Device Registration Service. SQL Server Express is not recommended to run in a high availability enterprise environment.



^{*} Windows 8.0 is supported when running the latest service pack from Microsoft.

[†] Prerequisite for Device Registration Service.

Download software

A single self-extracting ZIP file contains the installation software for AutoStore and Device Registration Service. Download the executable package from the *Nuance Web License Tool* and double-click it to unzip the contents to a temporary location on the computer. Before installing software, review the setup.htm file from the unzipped installation package.

After you expand the installation package, the AutoStore installation executable (AutoStore7SP3.exe) is located in the AutoStore Installation folder.

Turn off Microsoft Windows Firewall

Turn off Microsoft Windows Firewall before installing the AutoStore software and setting up your AutoStore environment. Turning off the firewall ensures that the AutoStore server can communicate with AutoStore components on the network. After you install AutoStore and set up your environment, you can turn on the firewall and coordinate with your network administrator to ensure that the firewall does not block access to the ports that the server and components use to communicate. If you cannot turn off the firewall because of security protocols, coordinate with your network administrator prior to installation to configure port access.

Refer to Microsoft Help for information on how to turn off Microsoft Windows Firewall.

The *Communication port reference* on page 23 topic provides more information on default port assignments for network-enabled components and lists port assignments that you can modify.



Install AutoStore

Complete the steps in this procedure for a new installation of the AutoStore software.

- 1. Turn on Microsoft Windows Updates to enable the installation wizard to install Microsoft Windows Identity Foundation.
 - **Tip:** If the installation wizard fails to install Microsoft Windows Identity Foundation, cancel the installation, verify that Microsoft Windows Updates is turned turn on, and restart the installation. You can restore the Microsoft Windows Updates settings after installing the AutoStore software.
- 2. Start the installation executable file from the AutoStore installation subfolder in the installation package described in *Download software* on page 6.

Administrator permissions are required to install AutoStore. Usually you can right-click the executable file (for example, AutoStore7.0SP3.exe) and click **Run as administrator**.

- 3. If the installation wizard prompts you to install required software, click Install.
- 4. After the installation wizard installs the required software, click Next.
- 5. Review and accept the license agreement.
- 6. On the Customer Information screen, type a user name and organization.
- 7. On the Custom Setup screen, select the AutoStore components that you want to install.
 - **Important:** By default, all capture and process components are selected for installation. Route components that require client software are not selected by default. If you select a route component that requires client software, verify that the client software is on the local machine. The installation fails if you select a route component and its client software is not on the machine.
- 8. If necessary, change the location where the installation wizard installs the software.

If you change the default location, use a location on the local machine. Do not use a location on a network drive.

9. On the Ready to Install the Program screen, click Install.

In AutoStore 7.0, some AutoStore 6.0 components were moved to a Sunset category. Sunset components are listed in the product release notes. Nuance no longer releases software updates for these components, although it still supports their use with AutoStore 7.0. Sunset components are not included in the default AutoStore installation. To install Sunset components, use **Software Updates** in AutoStore Process Designer to download and install the updates.



Upgrade a previous installation of AutoStore

You can run the AutoStore 7.0 installation executable to upgrade earlier versions of AutoStore 7.0 to AutoStore 7.0. To upgrade an AutoStore 6.0 server, you must first uninstall AutoStore before performing the AutoStore 7.0 installation.

Refer to information in the following topics to perform an upgrade.

- Upgrade checklist on page 8
- *Upgrade AutoStore* on page 8
- Upgrade with expired licenses on page 9

Upgrade checklist

Complete the items in the following checklist when upgrading from an earlier version of AutoStore 7.0 to AutoStore 7.0:

- □ Verify that you have administrator rights on the machine.
- □ Verify that your test and production environments satisfy the requirements described in *System requirements* on page 4.

Important: A simple upgrade is only supported for earlier installations of AutoStore 7.0.

For earlier versions of AutoStore (6 or earlier), you must first remove the earlier version of AutoStore before you install AutoStore 7.0.

When upgrading AutoStore 7.0 to the latest Service Pack, ensure that all AutoStore-related processes are stopped and that all AutoStore applications are closed.

Verify that your license maintenance contract is current.

Upgrade AutoStore

Complete the steps in this procedure to upgrade the AutoStore software from an earlier version of AutoStore 7.0.

Make sure that you stop the AutoStore service and close AutoStore application windows as described in this procedure before you begin the upgrade.

- 1. Review the Upgrade checklist on page 8.
- 2. Open AutoStore Process Designer.
- 3. On the Home ribbon, click Stop to stop the AutoStore service.
- 4. Close the AutoStore Process Designer window.



- 5. Close the AutoStore Status Monitor window if it is open.
- 6. Install the new version of the AutoStore software as described in *Install AutoStore* on page 7.
- 7. After the install program completes, open AutoStore Process Designer.
- 8. On the Home ribbon, click About, and verify that the about screen shows AutoStore 7.0.
- 9. On the Home ribbon, click Start to start the AutoStore service.
- 10. On the Home ribbon, click Status Monitor to start AutoStore Status Monitor.
- 11. If you installed the new AutoStore software in a test environment, use your test plan to test your workflows.

The evaluation license allows you to test before migrating the new software to the production environment.

12. After successful testing, migrate the new software to the production environment.

13. If necessary, license the AutoStore 7.0 components as described in *License AutoStore* on page 11.

Note: Existing AutoStore 7.0 licenses are migrated to AutoStore 7.0 during the upgrade.

Upgrade with expired licenses

To upgrade an environment with expired licenses, get a software maintenance key so you can download the AutoStore software.

- 1. Verify that your maintenance contract is active.
- 2. Type your Maintenance Contract ID and then click Get Key.

AutoStore Maintenance	×
Your maintenance license has expired.	
If you have purchased annual maintenance, you are entitled to free upgrades and free software patches for this product.	
To obtain your software maintenance license key please click on Get Key.	
Server ID: VMware564d7daa73751bdfd2748b7068fb28e58106354351	
Maintenance SN: 00131946	
Maintenance Contract ID:	
GetKey	
Unlock Key: OK	
Cancel	

The Software Maintenance page appears with the Maintenance Contract ID that you entered.



Software Maintenance	
If you have purchased annual maintenance, you are entitled to free upgrades a maintenance license please enter your contract number. If you have not purch reseller for details of various support and maintenance programs.	nd software patches for this product. To obtain your software ased annual maintenance, please contact your dealer or value added
Maintenance Contract ID:	
Submit >>	

3. Click Submit.

If the Maintenance Contract ID is valid, the next page shows your unlock key.



- 4. Right-click the selected text and click Copy to copy the key to the clipboard.
- 5. Paste the key in the Unlock Key field and click OK.

AutoStore Maintenance	×
Your maintenance license has expired.	
If you have purchased annual maintenance, you are entitled to free upgrades and free software patches for this product.	
To obtain your software maintenance license key please click on Get Key.	
Server ID: VMware564d7daa73751bdfd2748b7068fb28e58106354351	
Maintenance SN: 00131946	
Maintenance Contract ID:	
Get Key	
Unlock Key: OK	
Cancel	

6. Complete the procedure in *Upgrade AutoStore* on page 8.



License AutoStore

This procedure explains how to license AutoStore for a new installation and an installation in an environment that has active licenses.

- 1. On the Microsoft Windows taskbar, click Start > All Programs > Notable Solutions > AutoStore 7 > AutoStore 7 Process Designer.
- 2. On the Home tab of the ribbon, click the License Manager button.

On the Server tab, the AutoStore license appears as expired for a new installation:

License	Manag	er: VMwa	are4212	60f4dc	fdd67683b21ddb00f3f1631423272655l
Server	Capture	Process	Route	Other	Log
Name					License
AutoSto	ore				Expired
Softwar	e Mainten	ance			Evaluation (30 days remaining)

For environments that have active or expired licenses, the tab shows the licenses, their statuses, and the software maintenance status.

- 3. Click Create Request.
- 4. In the Save As dialog box, type a license file name and save the file locally. Note the file location.

🤤 Save As			
💮 💮 📕 🕶 Pro	gram Files (x86) 👻 Notable Solutions 👻 AutoStore 7 👻	🝷 த Search AutoStore 7	N
File name:	License		•
Save as type:			•
💽 <u>B</u> rowse Folders		Save	Cancel

5. Click Web License.

The Nuance Web License Tool page opens in a browser.

If you are a new user, continue with step 6 on page 11.

If you have a user account, go to step 7 on page 12.

- **6.** Create an account:
 - a) Click Create account
 - b) Enter the requested information and click Create My Account.



Last Name *	
Company *	
State/Province *	
Country	
United States	V
Confirm Email *	
Confirm Password *	
	Last Name * Company * State/Province * Country United States Confirm Email * Confirm Password *

Note: Do not use free email accounts such as Hotmail or Gmail.

- c) In the confirmation email that you receive, click the link to confirm your account registration. If the confirmation email is not in your inbox, check your SPAM folder or junk email folder.
- d) Return to the *Nuance Web License Tool* page.
- 7. Enter your login credentials and click Login.
- 8. Choose the AutoStore 7 in the Select Product box, and click Proceed to License Activation.



Software Download and Documents	
Select Product :	Software and Installation Guide
AutoStore 7 ·	AutoStore 7 Service Pack 3
	* Note: If your order is for a product upgrade, please refer to our Licensing desk. Licensing desk to get a license for your upgraded server."
	AutoStore 7 Installation Guide
	AutoStore 7 Admin Guide
	GAutoStore 7 Readme

- 9. Choose the license type from the License Type drop-down list box:
 - If you choose Evaluation/Extension, click **Browse** and browse to the license file that you created in step 4 on page 11. Click **Submit** and go to 13 on page 15.

Downloads License Activation License Type Production/NFR ✓		
License Activation icense Type roductionNFR	Downloads License	Activation
License Activation icense Type ProductionNFR Order and License Request License Request File Browse Server Friendly Name License/Activation Nut20bgCost is required		
Conse Type Conduction/NFR Conduction	icense Activation	
Order and License Request License Request File Brosse Server Friendly Name	cense Type	
Order and License Request License Request File Brosse Server Friendly Name	roduction/NFR	- U
License/Activation Number is required	Server Friendly Nam	e
THE PARTY AND A REPORT OF A	License/Activation N	unber
		and an and a second
	se/Activation N	Milling is required

• If you select **Production/NFR**, click **Browse** and browse to the license file that you created in step 4 on page 11. Enter a **License/Activation Number**. Click **Submit** and continue with step *10* on page 14.



NUANCE Web License Tool
Downloads License Activation
License Activation
License Type
Order and License Request
License Request File
C:tw orkingtLicense Browse
Server Friendly Name
License/Activation Number ield is required
Please do not click submit more than once
Submit >>

10. On the Product details page, specify the number of licenses and click Submit.



NUANCE Web License Tool	English +	Logout
Downloads Likense Activation		
Product details		
Please enter quantity for each product that you would like to license.		
Product Selection for Invoice: INV-87962-V0S8Q1 Product	Available Quantity	Quantity to License
AS Device License (1 to 9 tier) + 1 yr maintenance	93	•
File Import License (60K pages/Yr pack) (3 to 5 tier)	90	•
2D Barcode + 1 yr maintenance	90	0
Additional OCR Engine + 1 yr maintenance	40	
Mobile / WebCapture User License (20 pack) (1 to 9 tier) + 1 yr	90	
maintenance		
AutoStore for Datacap Basic Authentication and Communication	40	0

11. Click Download License.

NUANCE Web License Too	ol -	English -
Downloads License Activation Download License		
What to Expect Next		
You can download the License by clicking "Download License." shortly receive an email from Nuance with your license. Please your future reference.	In addition, you will keep this email for	
Download License		
Additional Resources		
Nuance wants to make sure your product deployment and day-t To that end, we have a myriad of resources you and your end-u	o-day use is successful. sers may find helpful:	
Nuance Knowledgebase		
Nuance Forums		
Nuance Product Training (On Demand eLearning)		
Nuance Video Tips and Tricks		
Nuance Newsletter		
· · · · · · · · · · · · · · · · · · ·		

12. Save the file locally and note the location of the file.

13. Open AutoStore Process Designer, and on the Home tab, click License Manager.





14. Click Load Keys and then select the location of the license file that was downloaded.

15. On the Load license keys dialog box, click OK.

License Manager: VMware564d7daa73 Server Capture Process Route Other	751bdfd2748b7068fb28e581	06354351	
Name	License		
Load license keys			
Name	Action	Status Before	Status After
AutoStore	Extend	Expired	E valuation (30 days remaining)
	Extend	Expired	Evaluation (30 days remaining) 5 Client(s);Volume: 2
PlacuShare (P)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
✓ DocuShare (R)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
V IKON DocSend	Extend	Expired	Evaluation (30 days remaining) 5 Device(s);Volume:.
Fortis (R)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
Fortis (P)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
ApplicationXtender (4.x) (P)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
ApplicationXtender (4.x) (R)	Extend	Expired	Evaluation (30 days remaining) (Volume: 2500 remai
Send to Printer (P)	Extend	Expired	Evaluation (30 days remaining) Support Image and .
Send to Printer (R)	Extend	Expired	Evaluation (30 days remaining) Support Image and .
Batch Importer	Extend	Expired	Evaluation (30 days remaining) (Volume: 2500 remai
Encryption	Extend	Expired	Evaluation (30 days remaining) (Volume: 2500 remai
Professional Barcode	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
Send to Folder	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
Send to FTP	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
🞸 LAN Fax	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
Hummingbird (5.x) (P)	Extend	Expired	Evaluation (30 days remaining) ;Volume: 2500 remai
-A11 1 11 105 3 (63)			E 1 / (00 1 11) V 1 0000 1
			,
			OK
< [▶ Help

The new license status appears.



AutoStore tutorial

To get familiar with AutoStore, complete the following tutorial. The tutorial explains how to use AutoStore Process Designer to design a simple task that routes documents from one folder to another folder.

- 1. Click Start on the Microsoft Windows taskbar and click All Programs > Notable Solutions > AutoStore 7 > AutoStore 7 Process Designer.
- 2. If Microsoft Windows prompts you for permission to make changes to the computer, click Yes.
- 3. On the AutoStore Process Designer ribbon, click License Manager to verify that the component licenses are current. If licenses are not current, review *License AutoStore* on page 11 or contact your Nuance sales representative for instructions.

File Home View		
New Open Close Save Send	Properties Add Delete Copy Paste A	range License Status Service Stor
File	Task	Manager Monitor Manager ID Rest Tools

4. Click New to create a configuration file.

Within the configuration, you create a workflow process with capture and route components. Type Sample in the Name field. Use the default values for the other options.

Task Properties	
General Administrator Alerts Scheduling Advanced	Activate Task Task information Name: Sample Comments:
	Perform this task Every: 20 - seconds If this task fails Retry Panaget 1 - times
	OK Cancel

5. In the Toolbox, expand Capture, Process and Route to show capture, process, and route components.





6. In the Capture tab, click and drag the Multi-Poll component onto the Sample configuration file workspace.



7. In the Route tab, click the Send to Folder component and drag it onto the workspace.

An arrow connects the components. The arrow shows the logical flow from the **Multi-Poll** component to the **Send to Folder** component.



File Hom	e View	Color	_ & ×
New Open O	Close Save Send	Properties Add Delete Copy Paste Arrange Imager ~ Monitor Manager Imager ~ Status Stop Help About Software Updates Task Task Tools Help About Software Updates	
Toolbox		- # CFG1	٩Þ×
N	<u>a</u>		
FortisBlue	GoogleDocs		
	- 12		Â
HP TRIM	Hummingbird/Open		
	Text eDOCS		
**	S		
IBM Content Manager OnDeman	IXOS		=
		Multi-Poll Send to Folder	
	Lasemche		
1			
Multi Router	OpenText Document Server, Alchemy		
	\bigcirc		
OpenText Livelink/Content	Output Manager Route		
Server			
RightFax Route	Send to Database		
	1		
Send to Database (Bulk)	Send to Folder	<	
1		Sample	
Send to FTP	Send to HTTP		

- 8. Double-click the Multi-Poll component on the workspace.
- 9. On the Folders tab, click Add Folders.

Multi-Poll		-	_	x
Folders Configurations RRTs' F	ormat Misc			
Add Folders Include Sut	ofolders Copy Paste	X Remove Folders		
Name Trav	verse Mask F	Priority Concurrent Poll	Configuration Pat	h
Folder Count: 0		OK	Cance	

10. Click Make New Folder, and create a folder to contain the files to be captured.

For this example, name the folder Capture.



Multi-Poll	Browse For Folder	n Path
Folder Count: 0		Cancel <u>H</u> elp

11. In the next Multi-Poll dialog box that appears, clear Remember the choice, and then click No. If you click Yes, the component captures all documents in the Capture folder and documents in subfolders.

Multi-Poll	-	x	J
Would you like	to include all :	subfolders?	
🗖 Remembe	r the choice		
	Yes	No	

12. Click the **Configurations** tab and then click the browse button (...).

Multi-Pol			-		x
Folders	Configurations	RRTs' Fo	ormat Misc		
	Names		# Component	Description	Type E
	Config1		1 Send to Folde	r Sends documents to one or more folder destination:	s. Roue
*					
Folder C	Count: 1			OK Cance	Help

The Send to Folder dialog box appears.

- 13. Configure the Send to Folder route component:
 - a) On the Send to Folder dialog box, click Add.
 - b) Click the Folder Path browse button (...).



Configurations	<u> </u>
General Sec	urity Impersonation Summary
<u>F</u> older Path:	
Normalize	e automatically Folder path/File names
🔲 🖸 verwrite	Existing File
🔲 <u>R</u> ename	File
<u>S</u> chema:	
	✓ Replace invalid characters with '_'
	Only add a counter when file exists
📃 <u>C</u> heck U:	ser Security
<u>U</u> ser Name:	
	OK Cancel <u>H</u> elp

c) On the Browse for Folder dialog box, click Make New Folder and make a destination folder named Route.

This folder stores all documents that have been captured to the Capture folder.

d) On the **Configurations** dialog box, use the default values.

Configurations						
General Secu	rity Impersonation Summary					
<u>F</u> older Path:	C:\Users\Administrator\Desktop\Route					
Normalize	<u>N</u> ormalize automatically Folder path/File names					
🔲 <u>O</u> verwrite	Existing File					
🔲 <u>R</u> ename F	ïle					
<u>S</u> chema:						
	✓ Replace invalid characters with '_'					
	Only add a counter when file exists					
📃 <u>C</u> heck Us	er Security					
<u>U</u> ser Name:						
	OK Cancel <u>H</u> elp					

14. On the AutoStore Process Designer ribbon, click Save and save the configuration file.

File	Home	View													
	2				3		Ph.		6		1	13 C		Start	
			-33		4		.e	ų j				0		Stop	
New	Open Close	Save	Send	Properties	Add		Сору		Arrange	License Manager 1	Status Monitor	Manager	∎⊳	Restart	Co
	File					Tas	k			_	Т	ools			
Toolbox - P CFG1															
~													_	_	



15. Click Start to start the AutoStore service.

File Home View				
New Open Close Save Send	Image: Status Status Status Status Properties Add Delete Copy Paste Arrange Icense Status Status Service Manager Manager Manager Namager	Cor		
File	Task Tools			
Toolbox CFG1				
1944		-		

16. Test the workflow by placing a file in the Capture folder.

AutoStore polls the folder according to the **Every** interval as shown in step 4 on page 17. When AutoStore finds the file, AutoStore routes it to the Route folder.



Communication port reference

The following tables provide general information on ports and protocols for AutoStore components. The component Help files contain information on configuring the components.

Component	Supported Authentication Types	Supports SSL for Data and Images?	Device Authentication Protocol
AutoCapture	Not supported	Yes	HTTP, HTTPS
Fuji Xerox AIP	Microsoft Windows, Custom Script	Yes	HTTP, HTTPS, Device
HP MFP/Digital Sender (OXPd)	Standard, Novell NetWare, Custom Plugin	Yes	HTTP, HTTPS
HP OXPd	Standard, Novell NetWare, Custom Plugin	Yes	HTTP, HTTPS
IMAP Capture	Not supported	Yes	IMAP
Konica Minolta iOption	Microsoft Windows, Custom Script	Yes	HTTPS
Konica Minolta MFP	Standard, Novell NetWare, Custom Plugin	Yes	SOAP/XML
Kyocera MFP (HyPAS) Microsoft Windows, Novell NetWare, Custom Script		Yes	HTTP, HTTPS
Lexmark MFP	Standard, Novell NetWare, Custom Plugin	Yes	HTTP, HTTPS
Output Manager Capture			
POP3 eMail	Not supported	Yes	SMTP
Ricoh Desktop SF	h Desktop SF Standard, Novell NetWare, Custom Plugin		HTTP, HTTPS
Ricoh ESA	Microsoft Windows, Active Directory, Novell	Yes	HTTP, HTTPS

Table 1: Capture Components (Table 1 of 2)



Component	Component Supported Authentication Types		Device Authentication Protocol
	NetWare, Script, Script (No Prompt)		
RightFax Capture	NT Authentication	The component relies on th e API. It does not control c ommunication protocols an d ports. Refer to the vendo r documentation for more i nformation.	Native
Samsung	Microsoft Windows, Custo m Script	No	НТТР
Samsung Smart UX	Microsoft Windows, Custo m Script	Yes	HTTP, HTTPS
Sharp MFP (OSA)	Microsoft Windows, Novell NetWare, Custom Script	No	HTTP, HTTPS
SMTP Capture	Not supported	No	Limited by IP address
Toshiba Unified Client	Microsoft Windows, Custo m Script	No	HTTP, HTTPS
Web Capture	Integrated Windows, Active Directory, LDAP, Custom Script	Yes	Integrated Windows, Active Directory, LDAP, Custom Script
Xerox EIP Connect	Microsoft Windows, Novell NetWare, Custom Script	No	HTTP, HTTPS, Device
Xerox WorkCentre Pro	Not supported	No	Native Device

Table 2: Capture Components (Table 2 of 2)

Component	Device Display Menu Protocol	Device File Transport Protocol	Default Communication Port Numbers	Port Modifiable?	Required Device Components and Notes
AutoCapture	HTTP, HTTPS	HTTP, HTTPS	8085	Yes	Client Client communicates with AutoStore server.



Component	Device Display Menu Protocol	Device File Transport Protocol	Default Communication Port Numbers	Port Modifiable?	Required Device Components and Notes
Fuji Xerox AIP	HTTP, HTTPS	FTP	Web server: 3242 FTP: 3281	Yes	
HP MFP/Digital Sender (OXPd)	HTTP, HTTPS	HTTP, HTTPS	HTTP: 3233 HTTPS: 3234	No	
HP OXPd	HTTP, HTTPS	HTTP, HTTPS	HTTP: 3233 HTTPS: 3234	No	HP OXPd package
IMAP Capture	Not supported	IMAP	143 SSL: 993	Yes	No applet
Konica Minolta iOption	HTTP, HTTPS	FTP/WebDAV	Web server: 3348 FTP: 3281 Application OpenAPI : 13351 Authority OpenAPI :13352 WebDAV: 13391	Yes	
Konica Minolta MFP	SOAP/XML	FTP/WebDAV	50001 SSL: 50003	Yes	
Kyocera MFP (HyPAS)	HTTP, HTTPS	HTTP, HTTPS	HTTP: 3250 HTTPS: 3251	Yes	Application package The application package is distributed with the component and is required to communicate with the AutoStore server.
Lexmark MFP	HTTP, HTTPS	HTTP, HTTPS	3233 SSL: 3234	Yes	The application package is distributed with the component and is required



Component	Device Display Menu Protocol	Device File Transport Protocol	Default Communication Port Numbers	Port Modifiable?	Required Device Components and Notes
					to communicate with the AutoStore server. It is a signed JAR file.
Output Manager Capture		Net.Tcp	8064	Yes	
POP3 eMail	Not supported	SMTP	110	Yes	Not applet
Ricoh Desktop SF Bicoh ESA	HTTP, HTTPS	HTTP, HTTPS	3233 SSL: 3234	Yes	The application package is distributed with the component and is required to communicate with the AutoStore server. It is a signed JAR file.
Ricoh ESA	нттр, нттру	нттр, нттру	8084	Yes	Xlet Java Xlet VM card with AutoStore Xlet on the device for communication with the AutoStore server.
RightFax Capture	Not supported	Native	Refer to RightFax documentation for more information.	No	
Samsung	НТТР	FTP/WebDAV	 Web application: 3349 FTP port: 3281 WebDAV port: 13392 	Yes	



Component	Device Display Menu Protocol	Device File Transport Protocol	Default Communication Port Numbers	Port Modifiable?	Required Device Components and Notes
Samsung Smart UX	HTTP, HTTPS	HTTP, HTTPS	3300	Yes	
Sharp MFP (OSA)	HTTP, HTTPS	FTP	3240	Yes	No applet IIS web application connects to the AutoStore web service. The device connects to the IIS web application.
SMTP Capture	Not applicable	SMTP	25	Yes	
Toshiba Unified Client	HTTP, HTTPS	HTTP, HTTPS	3310	Yes	
Web Capture	HTTP, HTTPS	HTTP, HTTPS	3290	Yes	No applet
Xerox EIP Connect	HTTP, HTTPS	FTP/SMB	3241	Yes	No applet IIS web application connects to the AutoStore web service. The device connects to the IIS web application.
Xerox WorkCentre Pro	FTP/SMB	FTP/SMB	21/SMB	FTP Port - Yes	No applet

Table 3: Additional Components

Component	Protocol	Default Communication Port Numbers	Port Modifiable?		
Autonomy WorkSite 9	The component relies on the API. It does not control communication protocols and ports.				
Box	HTTPS	443	Ν		



Component	Protocol	Default Communication Port Numbers	Port Modifiable?
d.3	Refer to d.3 vendor documentation for more information.	3400	Y
Datacap 8.1	HTTP and HTTPS for communicating with the server.	HTTP: 808 HTTPS: 443	Y
Documentum	HTTP, HTTPS, DFC	HTTP, HTTPS: No default DFC: 1489	Y
DocuShare	HTTP, HTTPS	HTTP on IIS: 80 HTTP on Tomcat: 8080 HTTPS: 443	Y
DocuWare	Native, HTTP, HTTPS	Native: Refer to DocuWare vendor documentation for more information. HTTP, HTTPS: No default	Native: N HTTP, HTTPS: Y
Dropbox	HTTP and HTTPS for the authorization service and communicating with the DMS.	Authorization service: 3240 DMS HTTP: 80 DMS HTTPS: 443	 Authorization service: Y DMS: N Refer to SharpBox API do cumentation for more infor mation on DMS implemen tations.
FileNet P8	HTTP, HTTPS	7001	Y
FileNet	Native	Refer to FileNet vendor documentation for more information.	N
Fortis	ODBC	TCP 1433 (SQL Server)/1521 (ORACLE)	Ν
FortisBlue	HTTP, HTTPS	No default	Y
GoogleDocs	HTTP, HTTPS	No default	Y



Component	Protocol	Default Communication Port Numbers	Port Modifiable?
HP TRIM	HTTP and HTTPS for communicating through web services. Protocol is unknown for client communication.	Communicating through web services: • HTTP: 80 • HTTPS: 443 Client communication: 1137	Communicating through web services: Y Client: Y
Hummingbird/Open Text eDOCS	Refer to Hummingbird/ Open Text eDOCS vendor documentation for more information.	No default	N
IBM Content Manager	Refer to IBM Content Manager vendor documentation for more information.	No default	N
IBM Content Manager OnDemand	Uses the Microsoft Windows File Management API for file operations.	Not applicable	Not applicable
Laserfiche	Native	No default	N
OpenText Document Server, Alchemy	Native	Refer to OpenText Document Server, Alchemy vendor documentation for more information	Refer to OpenText Document Server, Alchemy vendor documentation for more information
OpenText Livelink/Content Server	Native, HTTP, HTTPS	Native: 2099 HTTP: 80 HTTPS: 443	Y
Output Manager Route	Net.Tcp, HTTP, HTTPS	Net.Tcp: 8072 HTTP: 8066 HTTPS: 8067	N
RightfFax Route	Native	Refer to RightFax vendor documentation for more information	N



Nuance AutoStore Installation Guide Version 7.0 SP3

Component	Protocol	Default Communication Port Numbers	Port Modifiable?
Send to Database	Not applicable	TCP 1433 (SQL Server)/1521 (ORACLE)/ None	N
Send to Folder	Uses the Microsoft Windows File Management API for file operations.	Not applicable	Not applicable
Send to FTP	FTP	21	Y
Send to HTTP	HTTP, HTTPS	80	Y
Send to Mail Recipient	Native, SMTP, HTTP, HTTPS	Native: Refer to vendor documentation for more information. SMTP: 25, 465 HTTP: 80 HTTPS: 443	Native: N SMTP: Y HTTP, HTTPS: Y
Send to PC	TCP (for file transport)	3711	Y
Send to Printer	Port and protocol details are specific to the device and driver.	Not applicable	Not applicable
Send to SFTP	SFTP	22	Y
SharePoint 2007	HTTP, HTTPS	HTTP: 80 HTTPS: 443	Y
SharePoint 2010	HTTP, HTTPS	HTTP: 80 HTTPS: 443	Y
WebDAV Route	HTTP, HTTPS	HTTP: 80 HTTPS: 443	Y
Windream	DCOM, TCP/IP	 TCP/IP 32-bit: 534 TCP/IP 64-bit: 53464 	Ν
WORLDOX	NetBIOS	Native/NetBIOS	Ν



Troubleshooting tips

This topic provides tips for issues that have been identified while installing AutoStore.

Problem	Cause	Solution
Unable to license AutoStore server on an Intel NUC computer because of Invalid Server ID.	AutoStore requires the system serial number for licensing. The Inv alid Server ID message is received when licensing AutoStore if the serial number in the System Information is not set on an Intel Next Unit of Computing (NUC) computer.	The serial number on a NUC computer is part of the SMBIOS and may be set manually using the Intel Integrator Toolkit (ITK). The ITK is available for download at the <i>Intel</i> <i>Download Center</i> . Use the option to Customize this Computer's BIOS file to set an SMBIOS serial number with the ITK.

